
Siglent Waterfall

Release 0.1

Eric Waller

Jan 03, 2020

CONTENTS

1	Introduction	1
2	Usage	3
3	SiglentWaterfall Modules	5
3.1	Main	5
3.2	Background	5
3.3	Log	6
3.4	TwoDGraph	6
3.5	ThreeDGraph	6
4	License	9
5	Third Party Software	11
6	Indices and tables	13
	Python Module Index	15
	Index	17

INTRODUCTION

This program obtains trace information from a Siglent oscilloscope and displays them as a three dimension plot displaying a scrolling history of recent traces. The plot can be rotated and zoomed in our out using point devices.

The application is written in *Python3* on and uses multi-programming techniques to allow the program to use multiple cores.

Communication with the oscilloscope uses the *visa* instrument control infrastructure.

USAGE

To start the program from the command line, see the following usage.:

```
Usage: siglent [OPTIONS]
```

Siglent

Display a YT display and (optionally) a waterfall display of scope traces obtained from an SDS 1204X-E oscilloscope.

Options:

-r, --rows INTEGER	Rows in waterfall display (number of traces)
-c, --cols INTEGER	columns in waterfall display (samples/trace)
--waterfall	Show the 3D Display
--channel TEXT	Scope channel to capture (default=C1)
-n, --name TEXT	VISA Address of the oscilloscope [required]
-v, --verbose	Be verbose. Invoke twice for more verbosity
-L, --log-file PATH	Log file Name.
-t, --timeout INTEGER	Foreground process timeout in seconds (debug only)
-b, --bgttimeout INTEGER	Background process timeout in seconds (debug only)
--help	Show this message and exit.

For example:

```
siglent -n tcpip::192.168.1.201 -vv --waterfall
```

Will start the *Siglent Waterfall* program reading from the instrument at IP Address 192,168.1.201, being extremely verbose (debug level), and will display both the 2D and 3D displays.

```
siglent -n tcpip::192.168.1.201 -v
```

Will start the *Siglent Waterfall* program reading from the instrument at IP Address 192,168.1.201, being a little verbose (info level), and will display only 2D and 3D display.

SIGLENTWATERFALL MODULES

3.1 Main

3.2 Background

Generate a stream of vectors read from a siglent oscilloscope

class background.**Acquire** (*address, channel, cols*)
Acquire traces from the oscilloscope

This class sets up the oscilloscope, then reads data from it continuously, posting those trace information to a queue that is processed by the main program. This code is run in a multiprocessing environment allowing it to run independently of the main program. Hopefully, it runs on its own core.

Parameters

- **address** (*str*) – The *visa* address of the instrument
- **channel** (*str*) – The channel to read from the scope. Defaults to 'C1'. Values can be *C1*, *C2*, *C3*, *C4* or *math*
- **cols** (*int*) – The number of points to place in each vector. This controls the *skip factor* in the waveform setup. This decimates the 14K (or more) points in the scope memory down to a manageable number of points

update ()

Read the next trace from the oscilloscope

Read parameters as to the format and scale of the trace, read the raw data points, apply scale and offset information to the data

Returns: *False* if there is an error. Otherwise, return a tuple of two equal size lists of float. The first element is a list of *float* representing time values, and a list of *float* representing voltages.

exception background.**ScopeInitializationError**

background.**main** (*cols, timeout, address, channel, pipe*)
Stream traces from a Siglent oscilloscope to a pipe.

Read traces from a Siglent 1204x-E oscilloscope and stream those traces to the main program through a pipe. We also will receive commands through that pipe. Handle those commands and respond to those commands through the pipe as well. Commands and responses to those commands will be of the type 'Message' from the class defined above. The traces are sent as a 2-tuple of lists. The first list represents the time values of the samples, while the second list represents the voltages at the time values.

Parameters

- **cols** (*int*) – The expected size of the lists to be sent through the pipe.
- **timeout** (*int*) – The maximum time this process is to run. 0 implies no timeout
- **address** (*str*) – The *visa* address of the oscilloscope
- **channel** (*str*) – The name of the oscilloscope channel to stream.
- **pipe** (*pipe*) – The pipe through which data are communicated to and from the main program.

Returns *None*

Return type *None*

3.3 Log

`log.setLog(LogLevelStr)`

Set the log level to be used during this run. This program uses logging to provide warning, info, and debug level messages. Warnings are always enabled. info level messages are considered to be “Verbose”.

Parameters **LogLevelStr** – A string representing one of the members of logging that define log levels (“CRITICAL”, “DEBUG”, “ERROR”, “FATAL”, “INFO”, “NOTSET”, “WARN”, “WARNING”)

3.4 TwoDGraph

class `TwoDGraph.Graph(rows, title='YT Display')`

Create a window in which to display the YT display

The window contains two grids and the YT display. The axes are time, and amplitude.

Parameters **rows** (*int*) – Defines the horizontal size of plot in samples.

Keyword Arguments **title** (*str*) – The name of the window. Defaults to *YT Display*

```
np = <module 'numpy' from '/usr/lib/python3.8/site-packages/numpy/__init__.py'>
```

```
pg = <module 'pyqtgraph' from '/usr/lib/python3.8/site-packages/pyqtgraph/__init__.py'>
```

update (*data*)

Obtain next chunk of data, update the waterfall display

3.5 ThreeDGraph

class `ThreeDGraph.Graph(rows, cols, title='3D Waterfall Display', distance=50)`

Create a window in which to display the 3d display

The window contains two grids and the 3d display. The axes are time (history of former traces), time (for a given trace) and amplitude of the points in the trace. The grids are on the (history)time-amplitude and (history)time-time axes. No grid is generated for the (trace) time-amplitude axes so as not to occlude the line-of-site of the display

Parameters

- **rows** (*int*) – Defines the size of the waterfall in rows. This value represents the number of points per trace.

- **cols** (*int*) – Defines the size of the waterfall in columns. This value represents the depth of the storage. This is the number of traces to display

Keyword Arguments

- **title** (*str*) – The name of the waterfall window. Defaults to *3d Waterfall Display*
- **distance** (*int*) – The initial distance of the observer from the 3D display

```
np = <module 'numpy' from '/usr/lib/python3.8/site-packages/numpy/__init__.py'>
```

```
pg = <module 'pyqtgraph' from '/usr/lib/python3.8/site-packages/pyqtgraph/__init__.py'>
```

```
update(data)
```

Obtain next chunk of data, update the waterfall display

LICENSE

This program is licensed under the MIT license.

Copyright (c) 2020 Eric Waller

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

THIRD PARTY SOFTWARE

The following modules, not provided by Python or the *Siglent Waterfall* repository, are required at run time and are installed automatically by *pip*:

Module Name	Version	Description
Python	3.8	Interpreter
Click	7.0	Command line interface
numpy	17.4	Vector Math
PyOpenGL	3.1.0	3D graphics engine
PyQt5	5.13.2	GUI subsystem
PyQt5-sip	12.7.0	GUI subsystem
pyqtgraph	0.10.0	graphing package
pyVISA	1.10.1	Instrument control
scipy	1.3.3	Vector math

This program does use *Sphinx* to automatically generate documentation from the *doc* strings in the Python code itself. Sphinx can create man files, HTML files, pdf files, and others. This program uses the HTML documentation for the web application and pdf files for written manuals. It also generates man files for reference when running on Linux from a command line.

The following top level modules are required to build the documentation for this program suite. These modules may have dependencies of their own and are system dependent. These are not automatically installed.

Module Name	Version	Organization	Description
Sphinx	1.8.1	http://www.sphinx-doc.org/	Documentation Generator
texlive	2018.48568	http://tug.org/	Web Template Engine

To build the HTML documentation, from the root directory, run:

```
make html
```

To build the pdf documentation, from the root directory, run:

```
make latexpdf
```

To build the *man* documentation, from the root directory, run:

```
make man
```


INDICES AND TABLES

genindex modindex search

PYTHON MODULE INDEX

`__main__`, 5

b

`background`, 5

l

`log`, 6

t

`ThreeDGraph`, 6

`TwoDGraph`, 6

Symbols

`__main__` (*module*), 5

A

`Acquire` (*class in background*), 5

B

`background` (*module*), 5

G

`Graph` (*class in ThreeDGraph*), 6

`Graph` (*class in TwoDGraph*), 6

L

`log` (*module*), 6

M

`main()` (*in module background*), 5

N

`np` (*ThreeDGraph.Graph attribute*), 7

`np` (*TwoDGraph.Graph attribute*), 6

P

`pg` (*ThreeDGraph.Graph attribute*), 7

`pg` (*TwoDGraph.Graph attribute*), 6

S

`ScopeInitializationError`, 5

`setLog()` (*in module log*), 6

T

`ThreeDGraph` (*module*), 6

`TwoDGraph` (*module*), 6

U

`update()` (*background.Acquire method*), 5

`update()` (*ThreeDGraph.Graph method*), 7

`update()` (*TwoDGraph.Graph method*), 6